Raylogic GO PROTOCOL 0.4

Table of Contents

AREA LOAD SCENE	2
AREA CHANNEL DIRECT	4
RELAY PAIR ON	6
RELAY PAIR OFF	8
KEEP ALIVE SEND	10
QUERY DEVICE	13
QUERY DEVICE REPLY	

AREA LOAD SCENE

*	Α	R	=	0	0	0	F	0	1	0	1	0	0	CR

*AR=abcdefghij\r

ab = Unused = 00

cd = Function Number = 0F

ef = Area = 01

gh = Scene = 01

ij = Unused = 00

r = Delimiter = CR

ad,cd,ef,gh,ij are 2 digit ASCII HEX values \r = 1 character = CR or hex 0x0D Size of command = 15 bytes

*AR=000F010100\r

- Sending this command loads all channels assigned to Area 1 to SCENE 1, in all connected units
- 2. Valid Area values are 0x01 [1] to 0x10 [16].
- 3. Valid Scene values are 0x01 [1] to 0x3C [60] for all non LDX series products.
- 4. Scenes 0x3D [61] to 0x44 [68] recall SEQUENCES [1]-[8] in LDX-403.
- 5. Scenes 0x3D [61] to 0x4C [76] recall SEQUENCES [1]-[16] in LDX-300.
- Dimmers / Relays / Fans already assigned to the given Area all affected by this command.
- 7. Sending this command to the TCP-HUB will evoke a +AR40.... respone from all

- mods running dev f/w version 1.79 & above after 28/07/2020.
- 8. This allows instant channel type & level feedback from MODS in the area where the scene has been applied.

AREA CHANNEL DIRECT

*	Α	R	=	0	0	1	Α	0	1	0	1	0	1	CR

*AR=abcdefghij\r

ab = Unused = 00

cd = Function Number = 1A

ef = Area = 01

gh = Level = 01

ij = Channel = 01

r = Delimiter = CR

ad,cd,ef,gh,ij are 2 digit ASCII HEX values \r = 1 character = CR or hex 0x0D Size of command = 15 bytes

*AR=001A010101\r

- 1. Sending this command sets channel 1 in Area 1 to level 1
- 2. The command will execute only if Channel 1 is assigned to Area 1, else will not execute.
- 3. Valid Area values are 0x01 [1] to 0x10 [16].
- 4. Valid Channel values are 0x01 [1] to 0xFF [255].
- 5. The Level parameter will behave differently for various channel types.
- 6. For Dimmer channels Level 0x01 is maximum brightness, Level 0xFF is OFF.
- 7. For Switching channels [Relays] Level 0x01 = OFF, Level 0x02 = ON, Level

- 0x03 0xFF = ON for a duration [1] to [252] seconds. The relay will automatically switch OFF after this duration.
- 8. For Fan channels Level 0x01 = OFF, Level 0x02 = Speed 1, Level 0x03 = Speed 2, Level 0x04 = Speed 3, level 0x05 = Full Speed.
- 9. Sending this command to a MOD via the TCP HUB will evoke a +AR=.....
 response as a confirmation from all mods running dev f/w version 1.79 & above after 28/07/2020. The command sent will be an echo of the command received.

RELAY IN A PAIR ON

*	Α	R	=	0	0	2	7	0	1	0	1	1	4	CR

*AR=abcdefghij\r

ab = Unused = 00

cd = Function Number = 27

ef = Relay Pair = 01

gh = Relay No = 01

ij = Duration = 14

r = Delimiter = CR

ad,cd,ef,gh,ij are 2 digit ASCII HEX values
\r = 1 character = CR or hex 0x0D
Size of command = 15 bytes

*AR=0027010114\r

- 1. Sending this command sets Relay 1 in Pair 1 ON for a duration of 20 seconds.
- 2. Valid Relay Pair values are 0x01 [1] to 0x7F [127].
- 3. Valid Relay No. values are 0x01 [1st Relay] or 0x02 [2nd Relay].
- 4. Valid Duration values are 0x01 [1] to 0xFF [252] seconds. The relay will automatically switch OFF after this duration.
- 5. This command is used to OPEN or CLOSE curtain / screen motors by putting either of the relays ON for a duration.
- 6. This command will directly trigger channels irrespective of Area Channel

assignment.

7. Sending this command to a MOD via the TCP HUB will evoke a +AR=..... response as a confirmation from all mods running dev f/w version 1.79 & above after 28/07/2020. The command sent will be an echo of the command received.

RELAY PAIR OFF

*	Α	R	=	0	0	2	6	0	1	0	0	0	0	CR

*AR=abcdefghij\r

ab = Unused = 00

cd = Function Number = 26

ef = Relay Pair = 01

gh = Unused = 00

ij = Unused = 00

ad,cd,ef,gh,ij are 2 digit ASCII HEX values \r = 1 character = CR or hex 0x0D Size of command = 15 bytes

*AR=0026010000\r

- 1. Sending this command sets both relays in Pair 1 to OFF state.
- 2. Valid Relay Pair values are 0x01 [1] to 0x7F [127].
- 3. This command is used to instantly STOP curtain / screen motors.
- 4. This command will directly trigger channels irrespective of Area Channel assignment.
- 5. Sending this command to a MOD via the TCP HUB will evoke a +AR=.....
 response as a confirmation from all mods running dev f/w version 1.79 & above
 after 28/07/2020. The command sent will be an echo of the command

received.

KEEP ALIVE SEND

*	<	K	Α	=	0	1	CR	

*KA=01\r Size of command = 6 bytes

*KA=01\r

- 1. The TCP Hub must receive this command from every 3rd party automation system that is connected on PORT 5050
- 2. All 3rd Party automation systems receiving the KEEP ALIVE packet must send the same back to the server to maintain a persistent connection.
- 3. If the 3rd Party automation system does not receive this command, after initial connection to the server, it shall close its connection and reconnect to the server.
- 4. If theTCP HUB Server listening on PORT 5050 does not receive a KEEP ALIVE packet from a connected client the server will close the connection after 15-18 seconds and shift back to listen mode waiting for new connections.

QUERY DEVICE

?	А	R	4	0	=	0	1	CR			

?AR40=abc

ab = Start Address of GO device =
$$01$$
 c = Delimiter (\r) = CR

adb is a 2 digit ASCII HEX values \r = 1 character = CR or hex 0x0D Size of command = 9 bytes

$$2R=01\r$$

- 1. The 3rd party automation system may query a Raylogic GO device by sending this query.
- 2. The comand must contain the start address of the GO device being queried.
- 3. The start address is in a 2 digit ASCII HEX value
- 4. The GO device being queried will send a rreply using the QUERY DEVICE REPLY format.

QUERY DEVICE REPLY

+	Α	R	4	0	=	0	1	0	1	0	4	0	1	0	2	0	1	0	2	0	1	0	2	0	1	0	2	CR

+AR40=abcdefghijklmnopqrtsuvwxyzAAX

ab	= Start Address of GO device	= 01
cd	= Current Scene of GO device	= 01
ef	= Channel count of GO device	= 04
gh	= Channel 1 type	= 01
ij	= Channel 1 level	= 02
kl	= Channel 2 type	= 01
mn	= Channel 2 level	= 02
ор	= Channel 3 type	= 01
qr	= Channel 3 level	= 02
st	= Channel 4 type	= 01
uv	= Channel 4 level	= 02
WX	= Current running scheduler	= 00
yz	Current running timer	= 00
AA	= current running timer activity	= 00
X	= Delimiter (\r)	= CR

ab,cd,ef,gh,ij,kl,mn,op,qr,st,uv,uv,wx,yz,AA are 2 digit ASCII HEX values

X = 1 character = CR (\r) or hex 0x0D

Size of command = For MOD2 27 bytes Size of command = For MOD2F 23 bytes Size of command = For MOD4 35 bytes

 $2R40=01\r$ MOD 4 reply -> +AR40 =010104010201020102010200000\r

- 1. The GO device that is queried with the QUERY DEVICE command will reply using this format.
- 2. The reply contains the start address of the modules, current scene, number of channels and type and level for each channel.
- 3. The start address is a 2 digit ASCII HEX value. Valid values 01 to FF.
- 4. The current scene is a 2 digit ASCII HEX value. Valid values 01 to 3C (1 to 60)
- 5. The channel count is a 2 digit ASCII HEX value. MOD 4 sends 04, MOD 2 sends 02, MOD2F sends 01
- 6. The channel type is a 2 digit ASCII HEX value. 01 = Dimmer, 02 = Relay, 03 = Fan, 04 = Curtain pair
- 7. The channel level is a 2 digit ASCII HEX value.
- 8. For Dimmer channels Level 0x01 is maximum brightness, Level 0xFF is OFF.
- 9. For Switching channels [Relays] Level 0x01 = OFF, Level 0x02 = ON, Level 0x03 0xFF = ON for a duration [1] to [252] seconds. The relay will automatically switch OFF after this duration.
- 10. For Fan channels Level 0x01 = OFF, Level 0x02 = Speed 1, Level 0x03 = Speed 2, Level 0x04 = Speed 3, level 0x05 = Full Speed.